

NAG Library Routine Document

F06GGF (ZSWAP)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of ***bold italicised*** terms and other implementation-dependent details.

1 Purpose

F06GGF (ZSWAP) interchanges two n -element complex vectors x and y .

2 Specification

```
SUBROUTINE F06GGF (N, X, INCX, Y, INCY)
  INTEGER          N, INCX, INCY
  COMPLEX (KIND=nag_wp) X(*), Y(*)
```

The routine may be called by its BLAS name *zswap*.

3 Description

F06GGF (ZSWAP) interchanges the elements of complex vectors x and y scattered with stride INCX and INCY respectively.

4 References

Lawson C L, Hanson R J, Kincaid D R and Krogh F T (1979) Basic linear algebra subprograms for Fortran usage *ACM Trans. Math. Software* **5** 308–325

5 Arguments

- 1: N – INTEGER *Input*
On entry: n , the number of elements in x and y .
- 2: X(*) – COMPLEX (KIND=nag_wp) array *Input/Output*
Note: the dimension of the array X must be at least $\max(1, 1 + (N - 1) \times |\text{INCX}|)$.
On entry: the original vector x .
 If $\text{INCX} > 0$, x_i must be stored in $X(1 + (i - 1) \times \text{INCX})$, for $i = 1, 2, \dots, N$.
 If $\text{INCX} \leq 0$, x_i must be stored in $X(1 + (N - i) \times \text{INCX})$, for $i = 1, 2, \dots, N$.
On exit: the original vector y stored in the array elements used to store the original vector x . Intermediate elements of X are unchanged.
- 3: INCX – INTEGER *Input*
On entry: the increment in the subscripts of X between successive elements of x .
- 4: Y(*) – COMPLEX (KIND=nag_wp) array *Input/Output*
Note: the dimension of the array Y must be at least $\max(1, 1 + (N - 1) \times |\text{INCY}|)$.
On entry: the original vector y .
 If $\text{INCY} > 0$, y_i must be stored in $Y(1 + (i - 1) \times \text{INCY})$, for $i = 1, 2, \dots, N$.
 If $\text{INCY} \leq 0$, y_i must be stored in $Y(1 + (N - i) \times \text{INCY})$, for $i = 1, 2, \dots, N$.

On exit: the original vector x stored in the array elements used to store the original vector y . Intermediate elements of Y are unchanged.

5: INCY – INTEGER

Input

On entry: the increment in the subscripts of Y between successive elements of y .

6 Error Indicators and Warnings

None.

7 Accuracy

Not applicable.

8 Parallelism and Performance

F06GGF (ZSWAP) is not threaded in any implementation.

9 Further Comments

None.

10 Example

None.
